



Importare schema LDAP

In questo esempio si userà l'importo del schema di Pure FTP.

a) Creare il file pureftpd.schema con il seguente contenuto:

```
#
# pureftpd.schema
#
# Pure-FTPd User LDAP Schema
# See README.LDAP in the Pure-FTPd documentation for more information.
#
# Written by Ben Gertzfield <che =AT= debian -DOT- org>
#

## Pure-FTPd-related LDAP attributes

attributetype ( 1.3.6.1.4.1.6981.11.3.1 NAME 'FTPQuotaFiles'
    DESC 'Quota (in number of files) for an FTP user'
    EQUALITY integerMatch
    SYNTAX 1.3.6.1.4.1.1466.115.121.1.27 SINGLE-VALUE )

attributetype ( 1.3.6.1.4.1.6981.11.3.2 NAME 'FTPQuotaMBytes'
    DESC 'Quota (in megabytes) for an FTP user'
    EQUALITY integerMatch
    SYNTAX 1.3.6.1.4.1.1466.115.121.1.27 SINGLE-VALUE )

attributetype ( 1.3.6.1.4.1.6981.11.3.3 NAME 'FTPUploadRatio'
    DESC 'Ratio (compared with FTPRatioDown) for uploaded files'
    EQUALITY integerMatch
    SYNTAX 1.3.6.1.4.1.1466.115.121.1.27 SINGLE-VALUE )

attributetype ( 1.3.6.1.4.1.6981.11.3.4 NAME 'FTPDownloadRatio'
    DESC 'Ratio (compared with FTPRatioUp) for downloaded files'
    EQUALITY integerMatch
    SYNTAX 1.3.6.1.4.1.1466.115.121.1.27 SINGLE-VALUE )

attributetype ( 1.3.6.1.4.1.6981.11.3.5 NAME 'FTPUploadBandwidth'
    DESC 'Bandwidth (in KB/s) to limit upload speeds to'
    EQUALITY integerMatch
    SYNTAX 1.3.6.1.4.1.1466.115.121.1.27 SINGLE-VALUE )

attributetype ( 1.3.6.1.4.1.6981.11.3.6 NAME 'FTPDownloadBandwidth'
    DESC 'Bandwidth (in KB/s) to limit download speeds to'
    EQUALITY integerMatch
    SYNTAX 1.3.6.1.4.1.1466.115.121.1.27 SINGLE-VALUE )

attributetype ( 1.3.6.1.4.1.6981.11.3.7 NAME 'FTPStatus'
    DESC 'Account status: enabled or disabled'
    EQUALITY caseIgnoreIA5Match
    SYNTAX 1.3.6.1.4.1.1466.115.121.1.26 SINGLE-VALUE )

attributetype ( 1.3.6.1.4.1.6981.11.3.8 NAME 'FTPuid'
    DESC 'System uid (overrides uidNumber if present)'
    EQUALITY integerMatch
    SYNTAX 1.3.6.1.4.1.1466.115.121.1.27 SINGLE-VALUE )

attributetype ( 1.3.6.1.4.1.6981.11.3.9 NAME 'FTPgid'
    DESC 'System uid (overrides gidNumber if present)'
    EQUALITY integerMatch
    SYNTAX 1.3.6.1.4.1.1466.115.121.1.27 SINGLE-VALUE )

attributetype ( 1.3.6.1.4.1.6981.11.3.10 NAME 'FTPHomeDir'
    DESC 'FTP directory'
    EQUALITY caseIgnoreIA5Match
```



```
SYNTAX 1.3.6.1.4.1.1466.115.121.1.26 SINGLE-VALUE )
```

```
## New Pure-FTPd object type
```

```
objectclass ( 1.3.6.1.4.1.6981.11.2.3 NAME 'PureFTPdUser'
  DESC 'PureFTPd user with optional quota, throttling and ratio'
  SUP top AUXILIARY
  MAY ( FTPStatus $ FTPQuotaFiles $ FTPQuotaMBytes $ FTPUploadRatio $
    FTPDownloadRatio $ FTPUploadBandwidth $ FTPDownloadBandwidth $
    FTPuid $ FTPgid $ FTPHomeDir ) )
```

b) Copiare il file nelle seguenti cartelle:

- /etc/ldap/schema/
- /usr/share/univention-ldap/schema/
- /var/lib/univention-ldap/local-schema/

c) Aggiungere in /etc/ldap/slapd.conf :

```
# Indexes for Pure-FTPd LDAP attributes.
index FTPQuotaFiles,FTPQuotaMBytes eq,pres
index FTPUploadRatio,FTPDownloadRatio eq,pres
index FTPUploadBandwidth,FTPDownloadBandwidth eq,pres
index FTPStatus,FTPuid,FTPgid,FTPHomeDir eq,pres
```

d) Eseguire i seguenti cli:

- /usr/sbin/univention-config-registry commit /etc/ldap/slapd.conf
- /etc/init.d/slapd crestart

Creare gli attributi

Creare gli attributi secondo lo schema. Cioè. objectClass è PureFTPdUser e gli attributi con le loro caratteristiche sono:

- FTPHomeDir con valore string /var/ftp
- FTPgid con valore integer 1000
- FTPuid con valore integer 1000
- FTPStatus con valore string enabled/disabled

Usare il web per creare gli attributi. Andare su LDAP directory. Scegliere dal albero univention-custom attributes. Clicare su **add**. Andate su **Setting: Extended Attribute**. Compilare con il nome del attributo le seguenti:

- Unique name *
- UDM CLI name
- Short description *

a) In Module scegliete User.

b) In LDAP Mapping 'LDAP object class *' è PureFTPdUser e gli attributi secondo lista FTPHomeDir o FTPgid o FTPStatus oppure FTPuid. Clicare 'Remove object class if the attribute is removed'. Per ogni attributo si fa lo stesso procedimento.

c) In UMC inserisci 'Tab name' come il nome del attributo se si desidera.

d) In 'Data Type' scegli 'Edit after Creation'. Mettere i valori default come sopra indicato. Esempio. Per FTPuid e FTPgid inserire 1000. Il valore FTPStatus si puo cambiare nel utente. Se si mette il valore 'disabled', l'utente non puo accedere con FTP.

Config Pure FTP

Questa è la config giusta per l'ambiente 3D.

```
<code xml>##### # # # Sample Pure-FTPd LDAP
configuration file. # # See README.LDAP for explanations. # # #
#####
# Optional: scheme to connect with to LDAP server. Default: ldap # Other possible values: ldaps, ldapi, etc. # Remember to set
LDAPPort accordingly.
LDAPScheme ldap #VerboseLog yes
# Optional: name of the LDAP server. Default: localhost
LDAPServer 10.17.61.254 #LDAPServer 93.149.47.162
# Optional: server port. Default: 389
```



LDAPPort 7389

Mandatory: the base DN to search accounts from. No default.

LDAPBaseDN dc=3di,dc=it

Optional: who we should bind the server as. # Default: binds anonymously or binds as 'ftp' user

LDAPBindDN uid=Manager,dc=3di,dc=it

Password if we don't bind anonymously # This configuration file should be only readable by root

LDAPBindPW XcQ91YT3Tk5ToR2i

Optional: default UID, when there's no entry in a user object

LDAPDefaultUID 1000

Optional: default GID, when there's no entry in a user object

LDAPDefaultGID 1000

Filter to use to find the object that contains user info # \L is replaced by the login the user is trying to log in as # The default filter is (&(objectClass=posixAccount)(uid=\L))

#LDAPFilter (&(uid=%v)(objectclass=posixAccount)) LDAPFilter (&(objectClass=PureFTPdUser)(uid=\L)) #LDAPFilter
cn=ftpuser,cn=groups,dc=3di,dc=it

Attribute to get the home directory # Default is homeDirectory (the standard attribute from posixAccount)

LDAPHomeDir FTPHomeDir

LDAP protocol version to use # Version 3 (default) is mandatory with recent releases of OpenLDAP.

LDAPVersion 3

Optional: use TLS to connect to the LDAP server # Note: if ldaps scheme is used, this property has no effect # LDAPUseTLS True

Can be PASSWORD or BIND. # PASSWORD retrieves objects and checks against the userPassword attribute # BIND tries to bind

LDAPAuthMethod PASSWORD

Optional: default home directory if there's LDAPHomeDir entry

LDAPDefaultHomeDirectory /var/shared</CODE>