



Rimuovi un server dal dominio

```
/usr/share/univention-samba4/scripts/purge_s4_computer.py --computename=ucs-software
```

In caso ci sono degli errori nel drs dopo che si è fatto l'unjoin

```
ldbdel -H /var/lib/samba/private/sam.ldb \  
CN=UCS-BACKUP,CN=Servers,CN=Default-First-Site-Name,CN=Sites,CN=Configuration,DC=TREDI,DC=priv \  
--recursive
```

Aggiungere manualmente spn account

```
/usr/share/univention-samba4/scripts/create_spn_account.sh --samaccountname "dns-UCS02" --  
serviceprincipalname "DNS/UCS02.tredi.priv" --privatekeytab dns.keytab
```

Togliere i s4 e ucs reject

univention-s4connector-list-rejected

```
/usr/share/univention-s4-connector/remove_s4_rejected.py ou=rubrica,DC=tredi,DC=priv
```

```
/usr/share/univention-s4-connector/remove_ucs_rejected.py uid=dns-UCS02,cn=users,dc=3di,dc=it
```

Join manuale di un server

```
univention-join-dcname ucs01.tredi.priv
```

Avvio manuale degli join script

```
univention-run-join-scripts started
```

Altro

```
ldbdel -H /var/lib/samba/private/sam.ldb CN=dns-UCS02,CN=users,DC=tredi,DC=priv
```

```
ldbsearch -H /var/lib/samba/private/sam.ldb --cross-ncs
```

```
samba-tool dbcheck --cross-ncs --fix
```

```
/usr/share/univention-directory-notifier/univention-translog check --fix
```

```
/usr/share/univention-directory-notifier/univention-translog load 83853
```