




Scaricare il profilo VPN


Su questo indirizzo si scarica il profilo VPN: https://151.3.10.130/sslvpn_logon.shtml

Come creare Utenti VPN nel Firewall Watchguard

1. Creare Gruppo per VPN SSL



2. Impostare i campi come le preferenze.



3. Scegliere l'autenticazione



WatchGuard Fireware Web UI

User: admin

Mobile VPN with SSL

When you activate Mobile VPN with SSL, the "SSLVPN-Users" group and the "WatchGuard SSLVPN" policy are created to allow Mobile VPN with SSL connections from the Internet to the external interface.

☒ Activate Mobile VPN with SSL

General Authentication Advanced

Authentication Server Settings

Select one or more authentication servers. The first server in the list is the default authentication server.

SELECT	AUTHENTICATION SERVER
☒	Firebox-DB (Default)

DEFAULT

☐ Auto reconnect after a connection is lost

☐ Force users to authenticate after a connection is lost

☐ Allow the Mobile VPN with SSL client to remember password

Define users and groups to authenticate with Mobile VPN with SSL. The users and groups you define are automatically included in the "SSLVPN-Users" group.

☐	NAME	TYPE	AUTHENTICATION SERVER
☐	SSLVPN-Users	Group	Any

ADD REMOVE

SAVE

4. Impostare le DNS

WatchGuard Fireware Web UI

User: admin

Mobile VPN with SSL

When you activate Mobile VPN with SSL, the "SSLVPN-Users" group and the "WatchGuard SSLVPN" policy are created to allow Mobile VPN with SSL connections from the Internet to the external interface.

☒ Activate Mobile VPN with SSL

General Authentication Advanced

Authentication MDS

Encryption Blow fish

Data channel TCP 443

Configuration channel (TCP) 443

Keep-Alive Interval 10 seconds

Keep-Alive Timeout 60 seconds

Renegotiate Data Channel 61 minutes

DNS and WINS Servers

Domain Name

DNS Servers 10.17.61.33 80.90.80.90

WINS Servers

SAVE

5. Andare su Authentication-Servers-Firebox per creare gli Utenti



WatchGuard

DASHBOARD

SYSTEM STATUS

NETWORK

FIREWALL

SUBSCRIPTION SERVICES

AUTHENTICATION

Hotspot

Servers

Settings

Users and Groups

Web Server Certificate

Single Sign-On

Terminal Services

Authentication Portal

VPN

SYSTEM

Fireware Web UI

Servers / Firebox

Firebox Users

☐ Enable case-sensitivity for Firebox-DB user names

☐ USER

☐ enes

☐ akapilani

☐ agjoni

☐ mcali

ADD

EDIT

REMOVE

Firebox Groups

☐ GROUP

☐ VPN-Profile-Tirana

☐ SSLVPN-Users

ADD

EDIT

REMOVE

SAVE

CANCEL

Per gli Utenti esterni

Per gli Utenti esterni, dove si deve dare accesso solo certi IP. Si consiglia di usare il Mobile VPN with IPsec. Quindi va creato il gruppo, poi gli Utenti come nel caso del SSL.

WatchGuard

DASHBOARD

SYSTEM STATUS

NETWORK

FIREWALL

SUBSCRIPTION SERVICES

AUTHENTICATION

VPN

Branch Office VPN

BOVPN Virtual Interfaces

Phase2 Proposals

IKEv2 Shared Settings

Mobile VPN with IPsec

Mobile VPN with PPTP

Mobile VPN with SSL

Mobile VPN with L2TP

Global Settings

SYSTEM

Fireware Web UI

User: admin

Mobile VPN with IPsec

Groups

NAME	AUTHENTICATION SERVER	ALLOWED ACCESS	VIRTUAL IP POOL	IPSEC SETTINGS
VPN-Profile-Tirana	Firebox-DB	10.17.61.0/24 10.20.61.0/24	10.30.61.2-10.30.61.254	Auth: SHA1, Encr: AES (256-bit), I Negotiation Type: pre-shared-key

ADD

EDIT

REMOVE

Configuration File Generation

To generate a mobile VPN client configuration file, select a mobile user group from the list above, then select a VPN client and click Generate.

The Shrew Soft VPN client does not support all WatchGuard Mobile VPN with IPsec configuration settings. For a list of settings not supported by the Shrew Soft VPN client, click Help.

Client WatchGuard Mobile VPN GENERATE

Global Settings

☐ Make security policies read-only in the WatchGuard Mobile VPN client

SAVE